

# py-MEMdyn

## python MEMbrane dynamics

A Python package for Molecular Dynamics simulations in biological membranes

Manual V. 1.1

Xabier Bello, Mauricio Esguerra, David Rodriguez, Hugo Gutiérrez de Terán

hugo.gutierrez@icm.uu.se

*py-MEMdyn* is a python package developed to automate the process of setting up the simulation (via Molecular Dynamics (MD)) of G-protein Coupled Receptors (GPCR's) embedded in a cell membrane. The protocol can be adapted to insert other transmembrane proteins, not only GPCR's. The package is an implementation of a scripted recipe described in Gutiérrez de Terán et al. (2011) [1], and is being used in the web-based service for modeling and simulation of GPCR's available at <http://gpcr-modsim.org>.

## - DESCRIPTION

The fully automated pipeline available by using **py-MEMdyn** allows any researcher, without prior experience in computational chemistry, to perform an otherwise tedious and complex process of membrane insertion and thorough MD equilibration, as outlined in Figure 1.




Figure 1: Pipeline of the process followed to embed a G-protein Coupled Receptor into a cell membrane made of a POPC (Palmitoyl-Oleoyl-Phosphatidyl-Choline) phospholipid bilayer.

In the simplest scenario, only the receptor structure is considered. In such case the GPCR is automatically surrounded by a pre-equilibrated POPC (Palmitoyl-Oleoyl-Phosphatidyl-Choline) membrane model in a way that the TM (Trans-Membrane) bundle is parallel to the vertical axis of the membrane. The system is then soaked with bulk water and inserted into an hexagonal prism-shaped box, which is energy-minimized and carefully equilibrated in the framework of periodic boundary conditions (PBC). A thorough MD equilibration protocol lasting 5.0 ns follows.

But the simulation of an isolated receptor can only account for one part of the problem, and the influence of different non-protein elements in receptor dynamics such as the orthosteric (primary) ligand, allosteric modulator, or even specific cholesterol, lipid, water or ion molecules are key to a more comprehensive characterization of GPCR's. **py-MEMdyn** can explicitly handle these elements allowing a broader audience in the field of GPCR's

to use molecular dynamics simulations. These molecules should be uploaded in the same way they're present in the original PDB file of the receptor, so they are properly integrated into the membrane insertion protocol described above, together with force-field associated files (which can be either generated with external software like Macromodel, or by manual parameterization). In addition, it is also possible to perform MD simulations of receptor dimers, provided that a proper dimerization model exists (i.e., coming from X-ray crystallography or from a protein-protein docking protocol). The ease of use, flexibility and public availability of the **py-MEMdyn** package makes it a unique tool for researchers in the GPCR field interested in exploring dynamic processes of these receptors.

## - INSTALLATION

**py-MEMdyn** is a python package that can be used in any unix platform provided that the following dependencies are installed:

- git > V. 1.6.6 (for downloading)
- Python 2.7
- Gromacs 4.0.5 for version 1.0
- Gromacs 4.6.5 for version 1.1
- **A queuing system:**  
Although not strictly required, this is highly advisable since an MD simulation of 5.0 nanoseconds will be performed. However, if only membrane insertion and energy minimization is requested, this requirement can be avoided. Currently, the supported queuing systems include **SLURM** and **PBS**.

**py-MEMdyn** is hosted in a bitbucket repository at:

<https://bitbucket.org/gpcrmodsim/pymemdyn.git>

You can download any version of **py-MEMdyn** by cloning the repository to your local machine using git.

You will need to create a free personal account at bitbucket and send an e-mail to: [gpcruser@gmail.com](mailto:gpcruser@gmail.com) and you will be given access to the free repository.

To install **py-MEMdyn** follow these steps:

1. Clone the current version of **py-MEMdyn**

```
git clone https://username@bitbucket.org/gpcrmodsim/pymemdyn.git
```

Make sure to change *username* to the one you have created at bitbucket.

2. The previous command will create a *pymemdyn* directory. You now have to tell your operating system how to find that folder. You achieve this by declaring the location of the directory in a *.bashrc* file or *.cshrc* file in your home folder. An example of what you will have to include in your *.bashrc* file follows:

```
export PYMEMDYN=/home/username/software/pymemdyn
export PATH=$PYMEMDYN:$PATH
```

or if your shell is *csh* then in your *.cshrc* file you can add:

```
setenv PYMEMDYN /home/username/software/pymemdyn
set path = ($path $PYMEMDYN)
```

Notice that I have cloned *pymemdyn* in the software folder in my home folder, you will have to adapt this to wherever it is that you downloaded your *pymemdyn* to.

After including the route to your *pymemdyn* directory in your *.bashrc* file make sure to issue the command:

```
source .bashrc
```

or open a new terminal.

To check if you have defined the route to the *pymemdyn* directory correctly try to run the main program called *pymemdyn* in a terminal:

```
pymemdyn --help
```

You should obtain the following help output:

```
usage: pymemdyn [-h] [-v] [-b OWN_DIR] [-r REPO_DIR] -p PDB [-l LIGAND]
               [-a ALOSTERIC] [-w WATERS] [-i IONS] [-c CHO] [-q QUEUE] [-d]
```

```
== Setup Molecular Dynamics for Membrane Proteins given a PDB. ==
```

optional arguments:

```
-h, --help            show this help message and exit
-v, --version          show program's version number and exit
-b OWN_DIR             Working dir if different from actual dir
-r REPO_DIR            Path to templates of fixed files. If not provided,
                       take the value from settings.TEMPLATES_DIR.
-p PDB                Name of the pdb to insert into membrane for MD
                       (mandatory). Use the pdb extension. (e.g. -p
                       myprot.pdb)
-l LIGAND, --lig LIGAND
                       Name of the ligand, without extension. Three files
                       must be present along with the molecule pdb: the
                       ligand, its itp and its force field.
-a ALOSTERIC, --alo ALOSTERIC
                       Name of the allosteric interaction, without extension.
                       Three files must be present along with the molecule
                       pdb: the allosteric, its itp and its force field.
-w WATERS, --waters WATERS
                       Crystalized water molecules. File name without
                       extension.
-i IONS, --ions IONS   Crystalized ions file name without extension.
-c CHO, --cho CHO      Crystalized cholesterol molecules file name without
                       extension.
-q QUEUE, --queue QUEUE
                       Queueing system to use (slurm, pbs, pbs_ib and svgd
                       supported)
-d, --debug
```

3. Updates are very easy thanks to the git versioning system. Once **py-MEMdyn** has been downloaded into its own *pymemdyn* folder you just have to move to it and pull the newest changes:

```
cd /home/username/software/pymemdyn
git pull
```

4. You can also clone older stable versions of **py-MEMdyn**. For example the stable version 1.0 which works well and has been tested extensively against gromacs version 4.0.5 can be cloned with:

```
git clone https://username@bitbucket.org/gpcrmodsim/pymemdyn \
--branch stable/1.0 --single-branch pymemdyn-1.0
```

Now you will have to change your *.bashrc* or *.cshrc* files in your home folder accordingly.

5. To make sure that your gromacs installation is understood by **py-MEMdyn** you will need to specify the path to where Gromacs is installed in your system. To do this you will need to edit the *settings.py* file with any text editor (“vi” and “emacs” are common options in the unix environment). Make sure that only one line is uncommented, it should look like:

`GROMACS_PATH = /opt/gromacs4.6.5/bin`

Provided that in your case gromacs is installed in /opt. The program will prepend this line to the names of the binaries. So calling “grompp” will point to “/opt/gromacs4.6.5/bin/grompp”.

6. Similarly, in that file you specify which queuing system you are going to use to submit your dynamics runs. We assume you will use “slurm”, but you can use any of the possible options by uncommenting the one that best suits your system. You can also choose not to use any queuing system to run **py-MEMdyn** for testing in standalone in your desktop.

## - USE

- **COMPULSORY!** -p option:

In the simplest case, **py-MEMdyn** only needs a pdb file with the receptor. This should be readable by Gromacs (i.e., comply to PDB standards, see the GROMACS manual for details) and accessed from the working directory. If the -p switch is missing an error message informs you that this is the bare minimum you need to tell the program to perform an MD simulation. We will assume that the file is called gpcr.pdb. Thus:

```
pymemdyn -p gpcr.pdb
```

should work!

- Accessory options: A common user shouldn't need the -b, -r or -debug options: The working directory (OWN\_DIR) is set by default to that where the program has been invoked, and the repository (TEMPLATES\_DIR) is specified in the settings.py file (by default, templates/ subdirectory in the **py-MEMdyn** installation).
- Considering non-protein elements: ligand(s), structural waters, structural lipids, cholesterol molecules, explicit ions.
  - Option -l (specifying an orthosteric ligand). Lets assume that we have docked a ligand in the orthosteric binding site. We can include this in the simulation as long as we have generated the requested library and parameter files in gromacs. Thus, 3 files are needed, that should share a root name (i.e., lig):
    - \* lig.pdb: a standard pdb file where the atom names are explicitly considered in the itp and ff files (see bellow)
    - \* lig.itp: we refer to as the library file, and collects the atom charges and the bonded parameters (i.e., bonds, angles, dihedrals and torsions) as derived with the OPLS forcefield in the Gromacs standard nomenclature.
    - \* lig.ff: we will refer to as the “force-field file”, which collects the OPLS2005 atom types and non-bonded parameters in the Gromacs standard nomenclature. For the users used to Gromacs, this file is generally non-existing and the parameters listed here are merged onto the standard forcefield file in gromacs (i.e. ffoplsaa.itp). But in our protocol, this is needed as a separate file. pymemdyn -p gpcr.pdb -l lig
  - Option -alo (specifying an allosteric ligand): This should be treated exactly the same as the ligand: if the allosteric modulator is called allo, we need to have alo.pdb, alo.itp and alo.ff. pymemdyn -p gpcr.pdb -alo alo
  - Option -water (specifying structural waters): If structural waters are present (i.e., coming from an x-ray structure) these should be included as a separate pdb file (i.e. hoh.pdb). The corresponding itp file (hoh.itp) is also needed, but in this case the ff file is avoided as the parameters are in the standard forcefield.
  - Option -ions (specifying structural ions) If we want to consider structural ions (i.e., the sodium ion in the A2A high resolution structure 4EIY), we should name the needed files i.e. ion-local and provide the same information as in the case of structural waters: ion-local.pdb and ion-local.itp.
  - Option -cho (specifying cholesterol molecules): As in the previous case, the pdb and itp files are needed (i.e., cho.pdb and cho.itp).

- Option `--queue`: if other queue than the default one, indicated in the `settings.py`, is needed (in our example, `slurm` in `cuelebre`) this should be indicated in the option. Possibilities are listed in the `settings.py` file:
  - \* `slurm`
  - \* `pbs`
  - \* `pbs_ib infiniband`
  - \* `svgd`

To summarize, the following command should work for the most complex scenario:

```
pymemdyn -p gpcr.pdb --lig lig --waters hoh --alo alo --cho cho
```

## - RUNNING WITH QUEUES

≈ 90% of the time you will want to use some queuing system. We deal with queueing systems tweaks as we stumble upon them and it's out of our scope to cover them all. If you take a look at the `scripts` folder of the source code, you'll find some files called `"run_pbs.sh"`, `"run_svgd.sh"` and so on. Also there are specific queue objects in the source file `queue.py` we have to tweak for each queue. If you want to run your simulation in a supported queue, copy the `"run_queue_name.sh"` file to your working directory, and edit it. e.g. the script to submit an `a2a.pdb` simulation to `csb` queue looks like so:

```
#!/bin/bash
echo "#!/bin/bash -l"
source /home/apps/gromacs-4.6.5/bin/GMXRC.bash
source /home/apps/bin/apps.sh
pymemdyn -p a2a_ag.pdb -l lig --cho cho
" > temp.sh
chmod +x temp.sh
sbatch -n 8 -t 47:59:00 -J pymemdyn temp.sh
```

Now we just launch this script with:

```
./run_csb.sh
```

and wait for the results. Note that we launch 1 process, but flag the run as `mpi` with reservation of 8 cores in the `csb` cluster.

## - DEBUGGING

For debugging perhaps the first is to check that you have a well defined `settings.py` file. This you can do with the **pre-check.py** module like so:

```
python $PYMEMDYN/pre-check.py
```

Whenever you want to set up a new system, it's a good idea to just run a few steps of each stage in the equilibration protocol just to test that the `pdb` file is read correctly and the membrane-insertion protocol works fine and the system can be minimized and does not "explode" during the equilibration protocol (i.e., detect atom clashes and if other issues exist in your system).

To do this, use the `--debug` option, like:

```
pymemdyn -p gpcr.pdb --lig lig --waters hoh --debug
```

If everything works fine, you will see the list of output directories and files just as in a regular equilibration protocol, but with much smaller files (since we only use here 1000 steps of MD in each stage). NOTE that sometimes, due to the need of a smooth equilibration procedure (i.e. when a new ligand is introduced in the binding site without further refinement of the complex, or with slight clashes of existing water molecules) this kind of debugging equilibration procedure might crash during the first stages due to hot atoms or LINCX failure. This is normal, and you have two options: i) trust that the full equilibration procedure will fix the steric clashes in your starting system, and then directly run the `pymemdyn` without the debugging option, or ii) identify the hot atoms (check the `mdrun.log` file in the last subdirectory that was written in your output (generally `eq/mdrun.log` and look for "LINCX WARNING"). What if you want to check partial functions of `pymemdyn`? In order to do this you must edit the file `pymemdyn` and change:

1. Line 211 comment with “#” this line [that states: `run.clean()`], which is the one that deletes all the output files present in the working directory.
2. In the last two lines of this file, comment (add a “#”) the line: `run.moldyn()`
3. And uncomment (remove the “#”) the line: `run.light_moldyn()`
4. In the line 140 and within that block (`ligh_moldyn`) change the lines stating `steps = ["xxxx"]` and include only those steps that you want to test, which should be within a list of strings.

For the sake of clarity, these have been subdivided in two lines:

```
line 1-  steps = ["Init", "Minimization", "Equilibration", "Relax", "CARelax"]
```

Here you remove those strings that you do not want to be executed, i.e. if only membrane insertion and minimization is wished, remove "Equilibration", "Relax", "CARelax" so the line states:

```
steps    =  ["Init", "Minimization"]
```

```
line 2-  steps = ["CollectResults"]
```

This only accounts for the preparation of the output files for analysis, so if you only are interested on this stage, comment the previous line. The last assignment is the one that runs. NOTE that you must know what you do, otherwise you might have crashes in the code if needed files to run intermediate stages are missing!

## - OUTPUT

The performed equilibration includes the following stages:

STAGE	RESTRAINTS	FORCE CON- STANTS	TIME (ns)
Minimization			( $\approx$ 500 steps)
Equilibration	Protein Heavy Atoms	1000	0.5
		800	0.5
		600	0.5
		400	0.5
		200	0.5
	C- $\alpha$ Atoms	200	2.5

Table 1: Simulation steps performed by default using pyMEMdyn

In this folder you will find several files related to this simulation:

### INPUTS:

```
- popc.itp           # Topology of the lipids
- ffoplsaa_mod.itp   # Modified OPLSAA-FF, to account for lipid modifications
- ffoplsaabon_mod.itp # Modified OPLSAA-FF(bonded), to account for lipid modifications
- ffoplsaamb_mod.itp # Modified OPLSAA-FF(non-bonded), to account for lipid modifications
- topol.tpr          # Input for the first equilibration stage
- topol.top           # Topology of the system
- protein.itp         # Topology of the protein
- index.ndx           # Index file with appropriate groups for GROMACS
- prod_example.mdp    # Example of a parameter file to configure a production phase (see TIPS)
```

### STRUCTURES:

```
- hexagon.pdb        # Initial structure of the system, with the receptor centered in the box
- confout.gro         # Final structure of the system (see TIPS)
```

### TRAJECTORY FILES

```
- traj_EQ.xtc        # Trajectory of the whole system in .xtc format: 1 snapshot/50 ps
- ener_EQ.edr         # Energy file of the trajectory
```

## REPORTS:

In the "reports" subfolder, you will find the following files:

- tot\_ener.xvg, tot\_ener.log # System total energy plot and log
- temp.xvg, temp.log # System temperature plot and log
- pressure.xvg, pressure.log # System pressure plot and log
- volume.xvg, volume.log # System volume plot and log

## LOGS:

In the "logs" subfolder, you will find the log files of mdrun:

- eq\_{force\_constant}.log # log of stages with restrained heavy atoms of the receptor
- eqCA.log # log of the stage with restrained C-alfa atoms of the receptor

## - TIPS & TRICKS

- If you want to configure a .tpr input file for production phase, you can use the template 'prod.mdp' file by introducing the number steps (nsteps), and thus the simulation time, you want to run. After that, you just have to type:

```
grompp -f prod.mdp -c confout.gro -p topol.top -n index.ndx -o topol_prod.tpr
```

- If you want to create a PDB file of your system after the equilibration, with the receptor centered in the box, type:

```
echo 1 0 | trjconv -pbc mol -center -ur compact -f confout.gro -o confout.pdb
```

NOTE: these tips work for GROMACS version 4.0.5.

## REFERENCES

- [1] D. Rodríguez, A. Piñeiro, and H. Gutiérrez-de-Terán. 2011, Molecular dynamics simulations reveal insights into key structural elements of adenosine receptors. *Biochemistry*, **50**, 4194-4208.